magmodules



Link Placements

Cross-Linking for Magento 2

Where your cross-links actually ended up. Every time a page is rendered with a cross-link on it, the Cross-Linking extension notes which rule linked what, on which page, and how many links it inserted. This overview is that record — useful to see whether a rule is doing anything at all, to find pages that collect more links than you intended, and to check that a new rule landed where you expected.

Find it under **Marketing → Cross-Linking → Link Placements**.

What the columns mean

Column	What it tells you
Rule	The keywords of the rule that inserted the links
Content Type	Whether it was a product, a category, a CMS page, or content from another extension
Page	The product SKU, the category name with its ID, or the CMS page identifier
URL	The address of that page in the store view it was rendered for
Store View	Which store view the page was rendered for
Links	How many links that rule inserted the last time the page was rendered. A part of the page that the theme renders twice, such as a description that also feeds an excerpt, counts once
First Seen	The first render that put links on this page
Last Seen	The most recent one

What it records, and what it does not

It records renders, not visits. The extension can only see what it inserts at the moment a page is built. A page served from the full page cache is not built again, so its entry stays as it is — the links are still on the page, the date simply does not move. That is also why nothing is ever removed because a date got old on its own.

A rule that you change forgets what it did. Saving a rule clears its rows, because what it did is no longer what it does. They come back as pages are rendered again.

Content from another extension has no URL here. It is recorded with the identifier that extension passes along, but the extension knows its own addresses and this one does not.

Keeping it to a useful size

Two settings under **Stores → Configuration → Magmodules → Cross-Linking → General**:

- **Record Where Links Are Inserted** — switch the whole thing off if you do not want it. Nothing is written and the overview stays as it was.
- **Keep Placements For** — days a page stays listed after it was last rendered with a link. A nightly job removes the rest. A page that still carries the link is rendered again sooner or later and comes straight back, so what this clears out is pages that stopped being linked, or stopped existing. Set it to 0 to keep everything.

Clear Overview empties the list in one go. It fills again as pages are rendered.

Need More Help?

Documentation:

- All Help Articles - Complete documentation overview

Support:

- Contact Support - Get help from our team

For a complete overview of features and configuration options, see the Cross-Linking extension on magmodules.eu

All articles for Cross-Linking

Installation

1	Installatie met Composer (aanbevolen)
2	Installatie via de Adobe Marketplace
3	Installatie via FTP en SSH

Configuration

1	Configuratie Gids
2	Snelstart Gids

Troubleshooting

1	Troubleshooting

Other

1	Ontwikkelaarsgids

Grids

1	Cross-Links Grid
2	**Link Placements (current)**

Background

1	Best Practices
2	CLI Commando's

